



[Click here for larger picture](#)

Note - for those who prefer front side/back side tatting the text in *italics and red* indicates where the worker needs to use the second half of the ds first.

Abbreviations

R	ring	MB	move bead on core thread	SR	split ring	Cl	close
RW	reverse work	B	bead	Ch	chain +	Lj	lock join
CTM	continuous thread method			DNRW	do not reverse work		
SS	switch shuttle	B	bead	vsp	very small picot		

Wind 3 yards shuttle onto shuttle 1 and 2½ on shuttle 2 CTM with 1 B on each thread.

R1: 2 vsp 4 vsp 2 vsp 4 Cl DNRW SS

Ch: 8 SS

R2: 14 Cl RW

Ch: 10 + (last vsp R1) SLT RW

Ch: 6 Lj (next p R1) SS

SR3: 6 / 3 vsp 3 Cl

SR4: 5 / 2 vsp 2 vsp 1 Cl SS

LCh: 4 SS

R5: 14 Cl SS

LCh: 4 Lj (vsp SR4)

Ch: 3 Lj (next vsp SR4) vsp 4 Lj (vsp R3)

vsp 4 Lj (vsp R1) 4 SLT RW

Ch: vsp 1 RW

R6: 5 + (vsp last Ch) 5 Cl RW

Ch: 4 vsp 3 RW

R7: 5 + (next vsp last Ch) 5 Cl SS DNRW

Ch: 7 vsp 2 RW

R8: 4 + (vsp last Ch) 4 Cl RW

Ch: 4 vsp 3 vsp 3 RW

R9: 4 + (vsp next Ch of last row) 4 Cl SS DNRW

Ch: 4 vsp 1 Lj (vsp last Ch) 3 Lj (next vsp Ch) 4 vsp 4 RW

SR10: 4 + (vsp next Ch) 2 - 1 / 2 Cl

SR11: 2 - 1 - 1 - 2 / 5 Cl

SR12: 2 - 1 - 1 - 2 / 5 Cl

SR13: 2 - 1 - 1 - 2 / 4 vsp 1 Cl RW SS

R14: 1 + (vsp SR13) 5 - 5 vsp 1 Cl RW SS

SR15: 2 - 1 - 1 - 2 / 1 + (vsp R14) 4 Cl SS

Ch: 6 MB 1 vsp 1 SS

Move bead to back of hand

R16: 1 + (vsp Ch) 4 B 4 vsp 1 Cl SS

Ch: 1 + (vsp R16) 5 SS

SR17: 6 / 3 + (vsp on Ch front body) 3 Cl

SR18: 4 / 4 Cl

SR19: 6 / 3 + (vsp next Ch front body) 1 vsp 2 Cl SS

Ch: 9 SS

R20: 14 Cl RW

Ch: 10 T & C to vsp SR19




Fig. 1




Fig. 2




Fig. 3




Fig. 4