

Small Motif on Cabone Ring - © 2003 Jane Eborall amended in 2010



[Click here](#)

Materials:- No. 20 thread – two colours if required, 10 small beads, 1 cabone (curtain ring) in plastic or brass and measuring 5/8" and two shuttles. Finished item measures 1 1/2" in diameter.




Abbreviations:

Sh1	shuttle 1 (shuttle in right hand)	Sh2	shuttle 2 (shuttle in right hand)
CR	cabone ring	vsp	Very small picot
SR	Split Ring	^B	B at back of hand moved into place
T & C	Tie and cut	_B	B on core thread moved into place
LB	Large bead which should 'just' fit in the ring with a small space around it.		
LCh	Lock chain – 1 st half ds as usual, second half wrapped as in second side of SR		

Skills required – knowledge of split rings.

To add the bead to the centre of the CR first work the 3 doubles covering the end. Place the CR on top of the thread going over the back of the hand. Pull a loop from the thread at the back up through the CR and the large bead. Add a safety pin (or paperclip) to hold the bead (Fig. 1). Now pull another loop up from the back and up through the CR again (this will be at the base of the bead), take the shuttle through this loop and tighten (Fig. 2). Continue with next 3 ds & second half of SR (Fig. 3).

When joining to the large bead in SR10 pull the loop round the back of the hand up through the loop at the top of the bead (removing the safety pin at the same time), take the shuttle through the loop just formed and tighten. Continue the rest of the SR.



Place 10 beads on Sh2 before starting & leave an end of 12". Using Sh1
 SR1: 3 + (CR & LB – see 'how to' above) 3 / (remember long end of 12") 1 vsp 5 Cl
 SR2: 3 + (CR) 3 / 5 vsp 1 Cl RW SS bead at back of hand before next R
 R3: 1 + (vsp on last SR) 7 ^B 7 vsp 1 Cl RW SS
 SR4: 3 + (CR) 3 / 1 + (vsp on last R) 5 Cl
 SR5: 3 + (CR) 3 / 5 vsp 1 Cl RW SS bead at back of hand before next R
 R6: 1 + (vsp on last SR) 7 ^B 7 vsp 1 Cl RW SS

SR7: 3 + (CR) 3 / 1 + (vsp on last R) 5 CI
 SR8: 3 + (CR) 3 / 5 vsp 1 CI RW SS
 R9: 1 + (vsp SR8) 6 VLP (15 beads) 2 + (VLP) 6 vsp 1 CI RW SS
 SR10: 3 + (**CR & LB**) 3 / 1 + (R9) 5 CI
 SR11: 3 + (CR) 3 / 5 vsp 1 CI RW SS bead at back of hand before next R
 R12: 1 + (vsp on last SR) 7^B 7 vsp 1 CI RW SS
 SR13: 3 + (CR) 3 / 1 + (R12) 5 CI
 SR14: 3 + (CR) 3 / 5 vsp 1 CI RW SS bead at back of hand before next R
 R15: 1 + (vsp on last SR) 7^B 7 vsp 1 CI RW SS
 SR16: 3 + (CR) 3 / 1 + (vsp on last R) 5 CI
 SR17: 3 + (CR) 3 / 5 vsp 1 CI RW SS
 Cut Sh1 leaving a short length and work into the next SR covering the end.
 Using long end from SR1 finger tat the second side of next SR
 SR18: 1 + (vsp on SR17) 7 / 1 + (vsp on SR1) 7 Close SR and take long thread through remaining 2 beads on Sh2.
 Using the short end finger tat
 LCh: 15 SS and cut the end that you have just been using and hide it in the next ring.
 R19: 20 Cut and sew in end.




Fig. 4

My contact details [are here.](#)