

[Click here](#)[Click here](#)

Materials: No. 20 thread, bead measuring ¼" and 38 seed beads can be added to wings if required to replace picots.

Skills required: Knowledge of split rings.


Abbreviations

R	ring	Ch	chain
- or p	picot	SR	Split ring
vsp	Very small picot	SS	Switch shuttles
CR	Centre ring	RoCh	Ring on chain
CI	Close	RW	Reverse work
DNRW	Do not reverse work	+	join
Sh1	Shuttle 1	Sh2	Shuttle 2

Upper Wings – 2 shuttles.

Sh1 has 2 yards and Sh2 has 2 ½ yards

R1: 2 – 2 – 2 – 2 CI RW
 Ch: 8 RW
 R2: 2 + (R1) 2 – 2 – 2 CI RW
 Ch: 8 RW
 SR3: 2 + (R2) 2 / 3 vsp 1 RW SS
 R4: 1 + (vsp SR3) 6 – 6 vsp 1 RW SS
 SR5: 2 – 2 / 1 + (vsp R4) 3 CI RW
 Ch: 8 RW
 R6: 2 + (SR5) 2 + (R2) 2 – 2 CI RW
 Ch: 8 RW
 R7: 2 + (R6) 2 + (R1) 2 – 2 CI DNRW
 SR8: 2 – 2 – 2 / 2 CI DNRW
 SR9: 2 – 2 / 4 CI RW
 Ch: 6 vsp 1 DNRW SS
 RoCh10: 1 + (vsp Ch) 6 – 6 vsp 1 CI DNRW SS
 Ch: 1 + (vsp RoCh10) 6 RW
 SR11: 2 + (SR9) 2 / 4 CI DNRW
 SR12: 2 + (SR8) 2 – 2 / 2 CI RW
 Ch: 2 – 2 RW
 SR13: 2 – 2 – 2 / 2 CI DNRW
 SR14: 2 – 2 / 4 CI RW
 Ch: 6 vsp 1 SS DNRW
 RoCh15: 1 + (vsp Ch) 6 – 6 vsp 1 CI SS CI DNRW
 Ch: 1 + (vsp RoCh15) 6 RW
 SR16: 2 + (SR14) 2 / 4 CI DNRW
 SR17: 2 + (SR13) 2 – 2 / 2 CI DNRW
 R18: 2 – 2 – 2 – 2 CI RW
 Ch: 8 RW
 R19: 2 + (R18) 2 – 2 – 2 CI RW
 Ch: 8 RW
 SR20: 2 + (R19) 2 / 3 vsp 1 CI RW SS
 R21: 1 + (vsp SR20) 6 – 6 vsp 1 CI SS RW



SR22: 2 - 2 / 1 + (R21) 3 CI RW
 Ch: 8 RW
 R23: 2 + (SR22) 2 + (R19) 2 - 2 CI RW
 Ch: 8 RW
 R24: 2 + (R23) 2 + (R18) 2 - 2 CI T & C


Lower Wings & Body

If beads are required add 40 seed beads Sh2 (chain thread) and move into place to replace picots on the chains and on rings 5, 11, 17 and 23. Remember to place bead at back of hand before starting rings. Sh1 has 2 ¼ yards and Sh2 has 3 ½ yards

Make the centre 'ring' as follows. Take the thread through the centre bead. Place a safety pin or paper clip to hold in place (see Fig. 2). Make the CR as a CHAIN. If not winding shuttles CTM then the knot can be 'hidden' in the large bead.

Before starting the first double put another safety pin/paperclip in place to make a vsp - see Fig. 3.

CR: vsp 2 - 4 - 2 - 4 - 3 Lj (loop at start whilst removing pin/clip and continue the chain) 3 - 4 - 2 - 4 - 2. Lj to top of the bead removing the safety pin. SS See Fig. 4.



Sh1

Fig. 2




Fig. 3




Fig. 4

Joins to the upper wings are made by placing the upper wings BEHIND the work and bringing the joining thread up through the picot. **Hint - always have the points of the upper wings facing towards the worker.**

SR1: 2 / 2 CI SS DNRW

Ch: vsp 3 RW

R2: 2 + (R24 on upper wing taking the hook through the next picot on the CR and pulling up the loop from the work to join - the upper wing is held beneath the current work with the outer 'points' facing towards the worker and towards the right) 2 - 2 - 2 CI RW

Ch: 2 - 2 - 2 - 2 (if using beads do not add one to first p) RW

R3: 2 + (R2) 2 - 2 - 2 CI RW

Ch: 2 - 2 - 2 - 2 RW

SR4: 2 + (R3) 2 / 3 vsp 1 CI RW SS

R5: 1 + (SR4) 6 - 6 vsp 1 CI RW SS

SR6: 2 - 2 / 1 + (vsp R5) 3 CI RW

Ch: 2 - 2 - 2 - 2 RW

R7: 2 + (SR6) 2 + (R3) 2 - 2 CI RW

Ch: 2 - 2 - 2 - 2 RW

R8: 2 + (R7) 2 + (R2) 2 + (R18 on upper wing taking join through next p on CR and keeping upper wings BEHIND work as before) 2 CI DNRW

SR9: 2 + (R17 through the next p on CR) 2 - 2 / 2 CI DNRW

SR10: 2 - 2 / 4 CI RW

Ch: 2 - 2 - 2 - 2 vsp 1 SS DNRW

RoCh11: 1 + (vsp Ch) 6 - 6 vsp 1 CI SS

Ch: 1 + (vsp RoCh) 2 - 2 - 2 RW

SR12: 2 + (SR10) 2 / 4 CI

SR13: 2 + (SR9) 2 + (SR13 through next p CR) 2 / 2 CI RW

Ch: 1 vsp 1 SS DNRW

RoCh14: 1 + (vsp Ch) 4 - 4 vsp 1 CI SS

Ch: 1 + (vsp RoCh14) 1 RW

SR15: 2 + (SR12 through next p CR) 2 - 2 / 2 CI DNRW

SR16: 2 - 2 / 4 CI RW




Fig. 5

Ch: 2 - 2 - 2 vsp 1 SS DNRW
 RoCh17: 1 + (vsp Ch) 6 - 6 vsp 1 CI SS DNRW
 Ch: 1 + (vsp RoCh) 2 - 2 - 2 - 2 RW
 SR18: 2 + (SR16) 2 / 4 CI
 SR19: 2 + (SR15) 2 + (R8 through next p CR) 2 / 2 CI
 R20: 2 + (R7 through next p CR) 2 - 2 - 2 CI RW
 Ch: 2 - 2 - 2 - 2 RW
 R21: 2 + (R20) 2 - 2 - 2 CI RW
 Ch: 2 - 2 - 2 - 2 RW
 SR22: 2 + (R21) 2 / 3 vsp 1 RW SS
 R23: 1 + (vsp SR22) 6 - 6 vsp 1 RW SS
 SR24: 2 - 2 / 1 + (vsp R23) 3 CI RW
 Ch: 2 - 2 - 2 - 2 RW
 R25: 2 + (SR24) 2 + (R21) 2 - 2 CI RW
 Ch: 2 - 2 - 2 - 2 (if using beads do not add one to last p) RW
 R26: 2 + (R25) 2 + (R20) 2 +(R1 through next p CR) 2 CI RW
 Ch: 3 + (vsp base R1) SS
 SR27: 3 + (1st p of second Ch) 8 / 3 + (last p of second last Ch) 8 Close and cut ends to form feelers.
 If using beads for the eyes work final SR as follows. Move 1 bead to the back of hand before starting.
 SR27: 3 + (1st p of second Ch) 4 (move B from shuttle thread) 3 / 3 + (last p of second last Ch) 4 (move bead from back of hand next to last ds worked) 3 finish as before.